

# Axon Updates July 2024

---

The schedule for the **July 2024** release is as follows:

- Customers in the Enterprise region (.ent.evidence.com), Canada region (.ca.evidence.com), European region (.eur.evidence.com), European legacy region (.eu.evidence.com), and New Zealand receive on **July 23, 2024**.
- Customers in the U.S. Federal (.us.evidence.com) and U.S. Law Enforcement region (.evidence.com) receive on **July 24, 2024**.
- Customers in Australia, the United Kingdom, and South America region (.la.evidence.com) receive on **July 30, 2024**.

For information on the update schedule times for your region, refer to the [Axon Evidence Maintenance Schedule](#) on the Axon website.

We don't expect any downtime during this update.

Additional help documentation for the products included in these release notes is located at [axon.com/help](http://axon.com/help).

# Contents

---

<b>Digital evidence management</b>	<b>4</b>
Core platform changes	4
Final reminder: End-of-life for legacy sign-in	4
Axon Evidence	6
Axon Evidence	6
Axon Auto-Tagging	7
Axon Auto-Transcribe	8
Draft One	8
Evidence viewing and playback	8
Reporting	8
Third-Party Video Support	9
Mobile	9
Axon App	9
Axon Evidence Upload XT and XTMT	11
XTMT preview	11
Axon Academy	12
New e-learning videos	12
New course languages	12
Coming soon	16
Axon Evidence	16
<b>Cameras and sensors</b>	<b>18</b>
Axon Body 4	18
Operating system v1.2426	18
Axon Body 3	18
Operating system v1.32	18
Axon Body 3 and Axon Body 4	18
Role-based device settings	18
Axon Body Camera Dock	21
Universal login procedure	21
Axon Fleet 3	22
Firmware v2.2423	22
Axon ALPR	23
Record search	23
Axon View XL	25
Issue resolution: Uploads failing due to incorrect permission requirement	25
Issue resolution: Uploads failing due to session timeout	25
Improved application logging	26

Axon Academy .....	26
New e-learning videos .....	26
New course languages .....	26
<b>Axon Justice .....</b>	<b>30</b>
Updates and improvements .....	30
<b>Axon VR Training .....</b>	<b>31</b>
Coming soon .....	31
Simulator training version 2.0.6 .....	31
<b>Axon Investigate Version 4.1.1 (July 2024) .....</b>	<b>33</b>
<b>Change log .....</b>	<b>34</b>

# Digital evidence management

---

## Core platform changes

---

This section outlines foundational updates that affect all users. This includes things like sign-in updates, user management, and account management.

### Final reminder: End-of-life for legacy sign-in

**As previously announced, the legacy sign-in system shut off will be occurring this month, a few days prior to the monthly release.**

Over the past two years, Axon has upgraded all desktop and mobile applications to support our modern sign-in system, Universal Sign-In, enhancing security and reliability of our applications. We have gradually rolled out the new system across all applications and customers to minimize impact. The legacy sign-in system will be shut off this month prior to the July 2024 release. Axon Interview will not be impacted by this change, and Axon Interview customers will have until December 2024 to upgrade their systems.

As a reminder, the new system requires the use of multi-factor authentication (MFA) for all applications, including desktop and mobile clients (except for customers who have configured Single Sign-On). We strongly recommend users configure multiple MFA methods, such as app-based MFA, to minimize the impact of email or SMS delivery issues.

Following the shutdown, users attempting to access Axon desktop or mobile applications on unsupported versions will receive the following message. This can be resolved by upgrading to the latest version of that application.



## Update Required

This version of the application you are currently using is no longer supported. Update to the latest version of the application in order to sign in.

In order to avoid disruption, ensure your applications meet the minimum version requirements listed below:

Application name	Platform	Minimum version
Axon Capture	iOS	5.9.0
Axon Capture	Android	5.11.0
Axon Checkout	iOS	2.0.1
Axon Checkout	Android	0.4.1
Axon Device Manager	iOS	3.2.2
Axon Device Manager	Android	3.7.5
Axon Fleet Dashboard	iOS	No minimum version
Axon Fleet Dashboard	Android	No minimum version
Axon Fleet Dashboard	Windows	1.2.5395
Axon Respond	iOS	1.12
Axon Respond	Android	1.12
Axon View	iOS	5.8.0
Axon View	Android	5.7.0
Axon View XL	Windows	1.22
Axon Upload XT	Windows	2.6
Evidence Sync	Windows	3.22.1

Deprecated | [UI/Accessibility](#) | [Federal](#)

## Axon Evidence

---

### Axon Evidence

#### General updates and improvements

- Resolved an issue where TASER 10 cartridges were showing as Unrecognized when attaching cartridges to events.

- Resolved an issue with TASER 7 Use of Force logs not properly updating the current owner of a device.

Improvement | Federal

## Axon Auto-Tagging

### Custom metadata tagging

We are excited to announce the release of a new feature within Auto-Tagging called Custom Metadata Tagging. This enhancement enables organizations to tailor the Auto-Tagging service to their unique requirements by tagging custom metadata fields of video-evidence files using metadata exported from their CAD/RMS system.

#### Key features and benefits

- **Customizable tagging:** organizations can now configure Auto-Tagging to apply tags to specific custom metadata fields, allowing for greater flexibility and precision in organizing video-evidence files.
- **Enhanced searchability:** With custom metadata tags, users can improve the searchability and retrieval of video-evidence files, making it easier to locate specific files based on the custom metadata.

#### How it works

- **Configuration:** Organizations configure the custom metadata fields required for their evidence on Evidence.com. Auto-Tagging supports all types of fields including dropdown list, validated, freeform and multi-valued.
- **Metadata exports:** When exporting CAD/RMS data to CSV files, organizations include new columns with the prefix “Custom” to indicate that these new columns should be mapped to evidence’s custom metadata.
- **Auto-Tagging process:** Once the Custom Metadata Tagging flag is turned on by an Axon representative, all custom metadata fields of organization evidence will be auto populated by the corresponding “Custom” columns in the CSV files.
- **Search and retrieve:** Users can now leverage these custom metadata tags to search for and retrieve evidence files quickly and efficiently.

#### Getting started

To start using Custom Metadata Tagging, contact your Axon representative to modify your CAD exports and turn on the feature flag on Axon backend.

New | UI/Accessibility | Federal

# Axon Auto-Transcribe

## Improved Auto-Transcription models

### New Auto-Transcription models for both EN-US and FR-CA

We've improved our Auto-Transcription models for both United States English (en-us) and Canadian French (fr-ca) [Beta]. For United States English, users can expect improved word accuracy and speaker recognition for both indoor and outdoor environments. For Canadian French [Beta] we've improved overall word accuracy along with a focus on improving transcription of cardinal numbers. These updated models are automatically being used when auto-transcribing in these languages; no user action is required.

Improvement | Beta | Federal

## Draft One

### Settings permission update

Changing Draft One settings now only requires the "Edit Agency Settings" permission and no longer requires the actual "Draft One" permission.

Improvement | Admin | Federal

## Evidence viewing and playback

### Audit trail improvement

In the July release, the evidence audit trail has been enhanced to provide more detailed information about marker extraction activities. Users can now identify the newly extracted evidence title, ID and the URL from the audit trail of parent evidence. This improvement helps users track the chain of custody more easily.

Improvement | UI/Accessibility | Federal

## Reporting

A bug that caused serial number and device ID to not populate from reports has been fixed. Customers will no longer see this issue. They can also run reports retroactively from April - July to backfill the data.

Improvement | Federal

## Third-Party Video Support

Did you know Axon Evidence supports playback of aggregate directory-based third-party CCTV exports like those from **Milestone**, **Panasonic**, **Ocularis**, and **Synectics** systems? To learn more, [CLICK HERE](#).

If you encounter a video file format in which playback is not yet supported by Axon Evidence with Axon Third-Party Video Support, email [support@axon.com](mailto:support@axon.com) and provide details about the unsupported format.

Improvement | Federal

## Mobile

---

### Axon App

#### Axon App supports 25 LTF languages

Axon App supports 25 languages for all DEMS and RMS features within the app. The languages available match those listed in the User Profile on Evidence.com. This includes text translation, and localized date formats.

To change the app language

- **In the Axon iOS app:** Users go to device settings, choose their preferred language in their phone language settings, which will then apply to the Axon iOS app.

New | UI/Accessibility

### Accessibility improvements

We have made several accessibility improvements to the Axon App.


- Keyboard navigation and screen reader compatibility have been enhanced for drop-down menus, evidence cards, and filter icons.
- The video accessibility has been upgraded with our media package.
- Issues with aria-expanded attributes have been fixed to correctly announce expanded or collapsed states.
- Nested interactive elements in mobile dropdown fields have been resolved, and lists are now properly rendered.
- We have addressed issues related to page titles, visible focus, and on-focus actions.
- ARIA attributes and status message announcements have been improved for clearer interactions.

- Link clarity and the readability of hidden content have been enhanced, and form controls have been better grouped.
- Heading levels have been adjusted, and meaningful keyboard navigation sequences have been ensured for better content organization.

## Improvement | UI/Accessibility

### Time zone difference handling

We've improved how the Axon app handles time zones to enhance your experience. If your device's time zone differs from your user profile's time zone, the app will now display a dialog to notify you of the difference. The app consistently uses your profile's time zone to display dates and times, ensuring you always see accurate and relevant information, regardless of your device's settings. This update helps prevent confusion and ensures you have a consistent experience across all your devices.



## Improvement | UI/Accessibility

## Enhancements

We've made several improvements to the Axon app to enhance your user experience.

- The "My Evidences" section on the home page now accurately counts evidence from the last 30 days, ensuring you have up-to-date information.
- Keyboard navigation and focus management have been improved for better accessibility, making it easier for all users to navigate the app.
- The dictation UI in the report writer has been updated for a smoother and more efficient dictation experience.

These enhancements aim to provide a more accurate, accessible, and user-friendly interface.

Improvement | UI/Accessibility

## Axon Evidence Upload XT and XTMT

---

### XTMT preview

The latest XTMT Preview 2 was released in June with updated automation samples and tutorials.

XTMT (Upload XT Migration Tech) is a "low code/no code" solution designed to help organizations move legacy and physical media evidence from on-premise to Axon Evidence. It offers better reliability and greater scale of file migration than manually uploading through the Upload XT UI. The tool is fully scriptable and can be automated to upload, add metadata, create cases, and maintain folder structures of on-premise storage and server data.

If you would like to set up a demo of XTMT, get assistance planning and running migrations, or provide feedback about the latest Preview release please contact the Product Manager Matthew Carlson at [mcarlson@axon.com](mailto:mcarlson@axon.com) to request a slot for XTMT office hours.

Documentation and downloads: [XTMT Preview Guide](#)

Register for updates and early access and resources:

<https://forms.office.com/r/N5NufbJ9zC>

```

C:\Users\mcarlson\OneDrive - Axon Enterprise\Desktop\XTMT_UAT_v2.0.40>xtmt --xto "XTMT-CKO-Demo.xto" --allowDuplicates --skipParentFolder

  XTMT
  _____
  |   |   |   |   |
  |___|___|___|___|
  |   |   |   |   |
  |___|___|___|___|

Version: 2.0.40
Copyright (C) 2017-2023 Axon Enterprise. All Rights Reserved.
-----
Loading operation configuration: XTMT-CKO-Demo.xto
-----
Operation Name : "CKO-Demo-Test"
-----
Path       : C:\CKO
CaseName   : CKO-Test0114
CaseId     : 40248855-7689-493c-9337-7270573c67ec
Categories : Pending Review
-----
Enumerating files and folders. This may take a few minutes.
AllowDuplicates is set to true.
This will ingest 35 records that have already been ingested.
Found 35 files totalling 6 MB for this operation to upload in batches of 500
Ready to begin uploading
Press 'Y' to continue or 'X' to exit
Y
Initiating Uploading...

[01/17/2024 4:43 PM] Building upload batches
[01/17/2024 4:43 PM] e199aa96-3009-4f75-8534-18a4684fda24 Status: Batch waiting for processing
-----
[01/17/2024 4:43 PM] Operation "CKO-Demo-Test" Starting

```

**New** | **UI/Accessibility** | **Federal**

## Axon Academy

---

### New e-learning videos

You'll have access to the following new e-learning videos in July:

- **Axon App**
  - Getting Started with Axon App
  - Guide to Digital Evidence Management with Axon App
  - How to Create and Send Community Requests with Axon App

**New** | **Federal**

### New course languages

Additionally, you now also have access to 30 courses in 3 new languages: French (Canada), Spanish (Latin America), and Portuguese (Brazil). These courses include:

- DEMS e-learning, such as Evidence.com Admin and End User courses (French-Canadian only).

- TASER Instructor certification
- TASER Master Instructor certification, including electives.

**New** | **Federal**

## To access these courses

1. Go to the Academy homepage, and follow the steps outlined below to select a platform language.
2. On the Academy home page, look for international courses at the top of the page, under the “International Academy” header.
3. Select the desired language tile to discover available courses.


### Note

International TIS and MIS courses are not available for self-enrollment. Customers will need to contact local training teams to be enrolled.

## Step 1. Select Platform language

1. Select **Menu**.
2. Select **Choose your language**.


### 3. Select a language from the list.



## Step 2. Select desired language folder/tile.




## Step 3. View available courses in desired language.



### ***Are the login pathways localized in French, Spanish, and Portuguese?***

Yes. Users can log in via MyAxon or E.com SSO by setting the language selector located at the top of the login screen. Note, logging in via Brazilian Portuguese and Spanish will directly send the learners to Axon Academy homepage. Logging in via French will send learners to MyAxon. This is because MyAxon site is now also fully translated in French, whereas it is not currently supported in Spanish and Portuguese. This will cause an extra

“hop” for French learners in accessing Academy, but they will also be able to access localized MyAxon store, select Product Guides, etc.



## Coming soon

### Axon Evidence

#### Automated People Detection

We are thrilled to introduce Automated People Detection in Axon Evidence, a capability that will be available to all Pro-license users. This feature streamlines the way law enforcement professionals review video evidence by automatically detecting individuals captured with Axon Body 3 and Axon Body 4 cameras. Designed to address the challenge of the ever-increasing volume of video evidence, Automated People Detection significantly reduces the time required for evidence review when analyzing appearance of people.

Users will be able to initiate Automated People Detection for evidence and see thumbnails of all the people that appear in the video on the Evidence Search and Evidence Details pages. This allows users to quickly identify videos where people appear and jump to that moment, reducing the overall time to review evidence for relevant details.

**New** | **UI/Accessibility** | **Federal**

## Third-party Video Support

- Introducing playback support for IntraLogic Solutions (ILS) .exe formats.
- Updated support for Flir (formally DVTel) .dvt formats, and Genetec .g64x files.
- Improved handling of .re4 formats containing multiple streams of data.

Improvement | Federal

# Cameras and sensors

---

## Axon Body 4

---

### Operating system v1.2426

Starting with early access devices on July 22, this phased rollout is expected to span three weeks, targeting general availability by August 12th. This update includes:

- General bug fixes and improvements.

Improvement | Federal

## Axon Body 3

---

### Operating system v1.32

Starting with early access devices on July 23, this phased rollout is expected to span four weeks, targeting general availability by August 20th. This update includes:

- General bug fixes and improvements.

Improvement | Federal

## Axon Body 3 and Axon Body 4

---

### Role-based device settings

In July, Axon will release role-based device settings for Axon Body 3 and Axon Body 4 cameras. Previously, device settings were “one size fits all” across all devices registered to an organization. This new feature allows administrators to create unique copies of the Axon Body 3 and Axon Body 4 Device Settings page, called **Device Settings Profiles**. These profiles can then be associated with specific roles, so any cameras assigned to users in that role will operate with the profile’s settings. This new functionality will be available for all Axon Body 3 and Axon Body 4 users.

For example, the device settings page appears like this:

The screenshot shows the 'Axon Body 4 Camera Settings' page for the 'AB4 Device Profile - AB4 Default'. The page includes a navigation bar with tabs for EVIDENCE, RESPOND, CASES, INVENTORY, REPORTS, ADMIN, and HELP. Below the navigation bar, there are links for AXON BODY 4, AXON BODY 3, AXON BODY WORKFORCE, AXON BODY 2 & FLEX 2, AXON BODY 1 & FLEX 1, and BODY CAMERA WI-FI NETWORKS. The main content area has a title 'Axon Body 4 Camera Settings' and a subtitle 'AB4 Device Profile - AB4 Default'. A 'CREATE PROFILE' link is visible in the top right. Below the title, there is a text block: 'Adjust the settings of Axon Body 4 cameras with the current Device Settings Profile. To view and manage additional settings profiles the can be applied to different user roles, visit the [AB4 Settings Profiles](#)'. There are two input fields: 'PROFILE NAME' with the value 'AB4 Default' and 'ASSIGNED ROLES' with a dropdown menu showing 'All available roles'. A note below the fields states: 'AB4 cameras of all users with the selected roles will inherit the settings on this page. Roles on the default profile are available to be added to other profiles.'

Every Axon Evidence account begins with a default profile, which contains the current settings your organization already has configured for the camera. The default profile is associated with “All available roles”, meaning that every role and therefore every assigned camera in your organization utilizes the settings configured in the default profile. By selecting **Create Profile**, you can create a copy of the default profile and modify settings as needed.

For example, a test profile has been created:

The screenshot shows the 'Axon Body 4 Camera Settings' page for the 'AB4 Device Profile - Test Profile'. The page includes a navigation bar with tabs for EVIDENCE, RESPOND, CASES, INVENTORY, REPORTS, ADMIN, and HELP. Below the navigation bar, there are links for AXON BODY 4, AXON BODY 3, AXON BODY WORKFORCE, AXON BODY 2 & FLEX 2, AXON BODY 1 & FLEX 1, and BODY CAMERA WI-FI NETWORKS. The main content area has a title 'Axon Body 4 Camera Settings' and a subtitle 'AB4 Device Profile - Test Profile'. There are three links in the top right: 'VIEW ALL PROFILES', 'DUPLICATE PROFILE', and 'DELETE PROFILE'. Below the title, there is a text block: 'Adjust the settings of Axon Body 4 cameras with the current Device Settings Profile. To view and manage additional settings profiles the can be applied to different user roles, visit the [AB4 Settings Profiles](#)'. There are two input fields: 'PROFILE NAME' with the value 'Test Profile' and 'ASSIGNED ROLES' with a dropdown menu showing 'Select an item'. A note below the fields states: 'AB4 cameras of all users with the selected roles will inherit the settings on this page. Roles on the default profile are available to be added to other profiles.'

**Video**

**Quality**  
Determines the cameras' video recording quality.

- 1440p
- 1080p
- 720p Recommended
- 480p (Longest battery life)

**Body Worn Camera Field of View**  
Determines the Field of View of the Body Worn Camera. Setting this to 160 degrees will provide a wider field of view, while the 120 degrees setting will provide longer battery life.

- 160°
- 120°

Within this test profile, any settings can be uniquely configured without impacting the default profile. As a final step, you can select which existing roles should be associated with this new test profile. In the following example, the test profile is now associated with the armorer role. As shown in the image, any roles that are currently associated with another non-default profile are unavailable for selection here. In this example the investigator and user roles are assigned to a different profile titled “No Location Reporting”.

**Axon Body 4 Camera Settings** AB4 Device Profile - Test Profile VUE ALL PROFILES DUPLICATE PROFILE DELETE PROFILE

Adjust the settings of Axon Body 4 cameras with the current Device Settings Profile. To view and manage additional settings profiles the can be applied to different user roles, visit the [AB4 Settings Profiles](#)

PROFILE NAME	ASSIGNED ROLES
Test Profile	<ul style="list-style-type: none"> <li>Armorer <input checked="" type="checkbox"/></li> <li>Admin</li> <li>Investigator (Assigned to No Location Reporting)</li> <li>Lite Armorer</li> <li>Lite User</li> <li>User (Assigned to No Location Reporting)</li> <li>RecordingTester</li> </ul>

**Video**

**Quality**  
Determines the cameras' video resolution.

1440p  
 1080p  
 720p Recommended  
 480p (Longest battery life)

**Body Worn Camera Field of View**  
Determines the Field of View of the Body Worn Camera. Setting this to 160 degrees will provide a wider field of view, while the 120 degrees setting will provide longer battery life.

160°  
 120°

Selecting **View All Profiles** opens a list view of all profiles created and which roles are associated. From this view, you can select a specific profile to edit settings or role associations. This will be your new view every time you open the settings page going forward.

For a full step-by-step guide on how to configure this feature, please visit: [Role-Based Device Settings](#).

**New** | **UI/Accessibility** | **Federal**

# Axon Body Camera Dock

## Universal login procedure

Universal login is now active on all Docks running firmware version 3.17.

- **Login page:** With the new universal login workflow, the login page now shows only the domain name text box, and the **Save Changes** button is changed to **Continue**.

The screenshot shows the AXON Dock web interface. The top navigation bar includes 'AXON Dock', 'STATUS', 'NETWORKING', 'OPERATIONS', 'ADMINISTRATION', and 'FIRMWARE'. The main content area is titled 'OPERATIONS' and 'EVIDENCE.COM REGISTRATION'. It contains a text box for 'Evidence.com Agency' and a text box for 'Domain name'. Below these are two buttons: 'RESET REGISTRATION' and 'CONTINUE'. The 'CONTINUE' button is highlighted with a yellow box.

- **Verification:** After entering the domain name and selecting **Continue**, a verification URL and user code are shown.


The screenshot shows the AXON Dock web interface. The top navigation bar includes 'AXON Dock', 'STATUS', 'NETWORKING', 'OPERATIONS', 'ADMINISTRATION', and 'FIRMWARE'. The main content area is titled 'OPERATIONS' and 'EVIDENCE.COM REGISTRATION'. It contains a text box for 'Evidence.com Agency' and a text box for 'Domain name' with the value 'fwvn.qa.evidence.com'. Below these are two buttons: 'RESET REGISTRATION' and 'CONTINUE'. A yellow box highlights the verification message: 'Please open https://fwvn.qa.evidence.com/... and provide 123456789 to complete registration.'

- **Registration:** Selecting the verification link will prompt you for the verification code.


The screenshot shows a 'Sign in to a device' page. It contains a text box for 'Enter the code displayed on your device.' with the value 'E9VN72P9'. Below the text box is a blue button labeled 'CONTINUE'.

You will then be presented with one of the following two scenarios:

1. **First registration or expired login:** After entering the code, you will be prompted for the admin username and password.



2. **Non-expired login:** If the login isn't expired, the dock is directly registered after entering the registration code without requiring the username and password.



**New** | **UI/Accessibility** | **Federal**

## Axon Fleet 3

---

### Firmware v2.2423

Starting late July and continuing through early August, Axon will begin a phased deployment of firmware update version v2.2423 for the Axon Fleet 3 system.

### Fleet improvements

- **Simplified system deployment/initialization:** When deploying a new Fleet 3 system, the Fleet Dashboard application now supports registration and assignment of the Axon Signal Vehicle (ASV) device to the Fleet 3 vehicle identity, alleviating the need to navigate to Axon Evidence to populate this information.

- **Improved Wireless Mic reliability:** Resolved rare issues where the charging base could become disconnected from the Fleet 3 Hub, enhancing performance of audio capture.
- Improved connection reliability of body-worn cameras to the Fleet 3 Hub.
- Regular security and performance enhancements

## Fleet dashboard mobile

Fleet Dashboard for Android v1.2423 will be released to Google Play.

- Resolved ALPR notification issues, log duplication, and login errors.
- Enabled root detection to prevent unauthorized app use on rooted devices.
- Improved app stability and responsiveness by addressing crashes and other issues.

**Improvement** | **Federal**

# Axon ALPR

## Record search

This update includes the following improvements to the Axon Evidence ALPR Record Search feature:

### Search for multiple plates

When searching, you can now search for multiple plates of interest in a single search by separating each plate number with a comma. Wildcard searching, using the \* character, is also available when performing searches on multiple plate numbers.

The screenshot shows the Axon Evidence ALPR Record Search interface. The top navigation bar includes 'EVIDENCE', 'ALPR', 'RESPOND', 'CASES', 'INVENTORY', 'REPORTS', 'ADMIN', and 'HELP'. The 'ALPR' tab is selected. Below the navigation bar, there are tabs for 'HOTLIST RECORD', 'HOTLIST FILES', 'HOTLIST UPLOAD', 'RECORD SEARCH', and 'SNOOZED ALERTS'. The 'RECORD SEARCH' tab is active. The main content area is titled 'Record Search' and contains several search filters:
 

- PLATE NUMBER:** A text input field containing 'PLATE1, PLATE2, PLATE\*' is highlighted with a yellow border.
- OWNER:** A dropdown menu with 'Select Owner' as the current selection.
- VEHICLE:** A dropdown menu with 'Select Vehicle' as the current selection.
- SEARCH REASON:** A dropdown menu with 'Investigation' as the current selection.
- DATE:** Two date range inputs with 'X' icons for clearing. The first is '11/14/2023 12:00 AM' and the second is '07/09/2024 8:08 AM'.
- HIT/READ CATEGORY:** A dropdown menu with 'Select Type' as the current selection.

 At the bottom right of the search area, there are 'RESET FILTERS' and 'SEARCH' buttons.

### Interactive map markers

After completing an initial search, you can now hover over map markers for more detail on each hit or read record, removing the need to individually open each record. Users can opt to view the data above the map marker or pin it to the right side of the map panel for

ease of navigating records. Clicking ‘View’ on the panel shown will open the existing side detail panel for the record in question.

The screenshot displays a search interface for vehicle records. At the top, there are several filter fields: 'PLATE NUMBER' (empty), 'OWNER' (dropdown menu with 'Select Owner'), 'VEHICLE' (dropdown menu with 'Select Vehicle'), 'SEARCH REASON \*' (text input with 'Investigation'), 'DATE' (two date pickers with '11/14/2023 12:00 AM' and '07/09/2024 8:08 AM'), and 'HIT/READ CATEGORY' (dropdown menu with 'Select Type'). To the right of these filters are 'RESET FILTERS' and 'SEARCH' buttons.

Below the filters is a map of a region in Phoenix, Arizona, showing various roads and landmarks like 'Phoenix-Sonoran Preserve' and 'Cave Buttes Rec Area'. Several blue location pins are scattered across the map. A detail panel is open over one of the pins, displaying the following information:


- Plate Number: HSKYFB
- Owner: Masson, Chris
- Vehicle: Chris LPR101
- Capture Date: Feb 26, 2024 7:12 PM

The panel also includes a 'VIEW' button, a 'READ' button, and a small image thumbnail showing a night-time street scene. At the bottom right of the map area, there is a 'SEARCH IN THIS AREA' button. The map footer includes attribution to various data providers and 'Powered by Esri'.

### Map-based search

After completing an initial search, you can pan and zoom the map area, and using a new button titled ‘Search in this area’, perform a search with the same search parameters in the new map area, to expand or reduce the number of plates located. This can help when

searching for single or multiple vehicles of interest, but you require an ability to focus in on a specific geographic area for hit or read data.



Improvement | UI/Accessibility | Federal

## Axon View XL

### Issue resolution: Uploads failing due to incorrect permission requirement

The issue that incorrectly required users to have the [Upload External Files] permission enabled in evidence.com to successfully upload evidence has been addressed in the v1.27 release.

ViewXL has been updated to allow evidence uploads without requiring the Upload External Files permission.

### Issue resolution: Uploads failing due to session timeout

Corrected an issue where users whose active sessions expired were not being instructed to re-login to ViewXL prior to attempting to upload evidence. Proper error handling has been added to ViewXL in order to instruct users that re-authentication is required to successfully upload evidence.

Improvement | Federal

## Improved application logging

Added additional logging information to the authentication process for more efficient debugging and issue resolution.

**Improvement** | **Federal**

## Axon Academy

---

### New e-learning videos

You'll have access to the following new e-learning videos in July:

- **Fleet 3**
  - Fleet 3 Mobile - IOS
- **Axon Body 4**
  - Role-Based Settings

**New** | **Federal**

### New course languages

Additionally, you now also have access to 30 courses in 3 new languages: French (Canada), Spanish (Latin America), and Portuguese (Brazil). These courses include:

- Devices e-learning, such as Body 3 Admin and End User courses (French-Canadian only).

**New** | **Federal**

### To access these courses


1. Go to the Academy homepage, and follow the steps outlined below to select a platform language.
2. On the Academy home page, look for international courses at the top of the page, under the “International Academy” header.
3. Select the desired language tile to discover available courses.

#### Note

International TIS and MIS courses are not available for self-enrollment. Customers will need to contact local training teams to be enrolled.

## Step 1. Select Platform language


1. Select **Menu**.
2. Select **Choose your language**.
3. Select a language from the list.



## Step 2. Select desired language folder/tile.




## Step 3. View available courses in desired language.



### ***Are the login pathways localized in French, Spanish, and Portuguese?***

Yes. Users can log in via MyAxon or E.com SSO by setting the language selector located at the top of the login screen. Note, logging in via Brazilian Portuguese and Spanish will directly send the learners to Axon Academy homepage. Logging in via French will send learners to MyAxon. This is because MyAxon site is now also fully translated in French, whereas it is not currently supported in Spanish and Portuguese. This will cause an extra

“hop” for French learners in accessing Academy, but they will also be able to access localized MyAxon store, select Product Guides, etc.



# Axon Justice

---

## Updates and improvements

---

- Evidence “collected by” data will now display the user assigned from the originating organization.
- Resolved an error encountered when adding a user to a group in the access list. End users can now add a user to the internal access list when the group list has been expanded.
- The API client value “uploaded by” is now consistent across evidence search, evidence details, and case view.

Improvement | UI/Accessibility | Federal

# Axon VR Training

---

## Coming soon

---

### Simulator training version 2.0.6

This update, scheduled for release soon, includes the following content and releases. Once released, ensure you have a VR Handgun VR Controller and your Focus 3 headsets is updated to ROM version 5.1.999.909 or later to use it.


#### New

### Simulator training range skill exercises

#### Handgun targets

In this exercise, trainees enhance situational awareness and mental processing under cognitive load. Using a handgun, they receive variable targeting instructions, requiring positive target identification and accurate engagement of targets with various shapes, colors, and symbols positioned at different distances, heights, and angles. The variety of combinations creates a wide array of shooting challenges, helping trainees develop proficiency with the fundamentals of marksmanship and strengthen operational confidence in real-world scenarios.

In conjunction with this range skill exercise, a Facilitator's Guide will be available in Axon Academy. This guide will be intended to support trainers implementing this exercise into their training curriculum, as well as facilitate debriefs with their trainees post-training.




#### Weapon transitions

In this exercise, trainees enhance their proficiency in transitioning between a TASER energy weapon and a handgun. In response to randomized verbal commands, they practice quick and efficient weapon transitions to improve response times in dynamic

situations. Through repeated and deliberate practice, trainees develop muscle memory and understand safety protocols to reduce the risk of accidental discharges or weapon confusion.

In conjunction with this range skill exercise, a Facilitator's Guide will be available in Axon Academy. This guide will be intended to support trainers implementing this exercise into their training curriculum, as well as facilitate debriefs with their trainees post-training.



# Axon Investigate Version 4.1.1 (July 2024)

---

The release of Axon Investigate 4.1.1 is a patch release to address the following issues:

- Downloading selected evidence items from Axon Evidence into Investigate using the “Open With” control in Axon Evidence was not honoring whether the user was allowed to download per the role/permission set at the organization-level.
- Slow performance with loading projects/files and playback.
- Mark image hotkey not working.
- Ability to select multiple metadata tags of the same category in the search/filter/sort menu.
- The Narrative Report included an extra blank signature page.
- Drag/drop not loading files into the Camera Match Overlay tool.
- New lightboard project selection crashing the application.

This release does not include new features or processes. Therefore, accredited laboratories using this software are not bound to feature validation, per ISO accreditation, prior to use.

Improvement | Federal

# Change log

---

The table below contains a log of all changes made to these release notes.

Date	Product	Description of Change
July 16, 2024	Initial notes created	
July 17, 2024	Auto-Transcribe	Removed Auto-Transcribe feature flag description section.
July 18, 2024	ViewXL	Version 1.27 added.
July 22, 2024	Axon Reporting	Resolved bug added

If you have any questions about the information in this release, contact your Axon representative or Technical Support.

1-800-978-2737 ext. 4

[support@axon.com](mailto:support@axon.com)

Do you have feedback about Axon's release notes? Submit it [here](#).

Sincerely,

The Axon Team

Axon Enterprise, Inc.