

Axon Updates September 2026

Release schedule

The Axon **September 2026** release is scheduled by region on the dates listed in each product's release notes. These dates indicate when updates are deployed, not when features become available. Feature availability varies by product and region and is subject to change.

For Records and Standards, see the [Productivity page](#) for release dates.

We do not expect any downtime during these updates.

Learn more about the [Axon Cloud Services Maintenance Schedule](#).

Additional help documentation for the products included in these release notes is located at <https://www.axon.com/help/release-notes.htm>.

Contents

Digital evidence management	5
Core platform updates	5
Embedded Group audit trail	5
Parent file relationship in evidence audit trail	5
Partner API updates	5
Changes to search API pagination limits	5
Changes to search API rate limits	6
Axon Evidence	6
AI Generated Summaries of Images and Documents	6
Attribute Search	6
Bulk metadata actions support up to 5,000 items	7
New Investigate Side Panel in Axon Evidence	7
Redesigned document viewer	7
Stabilization in Clarifications	8
Video Stitching moves to a side panel	8
Axon Auto-Tagging	8
Voice tagging in AI Auto-Tagging (Alpha release)	8
Axon Community Request	9
Configure custom metadata for requests	9
Expanded Victim and Community notification workflows	9
Increased file upload limits for Community Request	9
My90 is moving to Community Surveys	9
Case Management	11
Advanced Sharing is available for early access in the UK	11
Case identifiers in download link emails and file names	11
Control automatic evidence sharing with partner organizations	12
Evidence Certificates in Advanced Sharing policies	12
Evidence Share Log in Advanced Sharing policies	12
Include marker reports in download packages	12
Evidence viewing and playback	13
Play up to 12 videos in Multicam Playback	13
Third-Party Video playback for records management uploads	13
View and extract embedded subtitles	13
Zip Preview support for Deflate64	13
Redaction	14
Redaction templates	14
Refreshed Redaction Studio layout and navigation	14
Third Party Video Support	14

Expanded format support and improvements	14
Axon Capture	16
Axon Capture is retiring	16
Axon View	16
Axon View is retiring	16
Evidence Upload XT	17
Close exits Upload XT when no upload is running	17
Faster case and tag loading	17
TSV file import in the Migration tab	17
Resolved issues	18
Axon Evidence	18
Coming soon	18
Axon Evidence	18
Cameras and sensors	19
Axon Body 4	19
Firmware Update Process Improvement for Axon Body Cameras	19
Firmware v1.2631 Releasing September 22nd	19
Axon Body 3	19
Firmware Update Process Improvement for Axon Body Cameras	19
Firmware v1.2631 Releasing September 22nd	20
Axon Body Workforce	20
Firmware Update Process Improvement for Axon Body Cameras	20
Axon Body Mini	20
Firmware Update Process Improvement for Axon Body Cameras	20
Axon Fleet	21
Disable ALPR Fleet Search in Axon Evidence (US1)	21
Fleet 2026 Q4 Interim Release v2.2634.4950	21
Axon ALPR	21
Disable ALPR Fleet Search in Axon Evidence (US1)	21
Axon Device Manager	22
Axon Device Manager (ADM) v3.2631 Quality Improvements	22
Resolved issues	22
Axon Body 4	22
Axon Body 3	22
Coming soon	23
Axon Body 3	23
Axon ALPR	23
Axon View XL	24

TASER Energy Weapons **25**

 Axon Dock firmware 3.25 25

 TASER 10 Probe Connection Summary 25

 TASER Weapons Health Digest 25

 TREND TASER 10 Quarterly Report 26

 TREND in Axon Evidence 26

 Resolved issues 26

Justice **28**

 AI Generated Summaries of Images and Documents 28

 Bulk actions on evidence 28

 Redesigned document viewer 28

 Stabilization in Clarifications 29

 Video Stitching moves to a side panel 29

 Coming soon 29

 A Stitch control on the evidence toolbar 29

Change log **31**

Digital evidence management

Core platform updates

Embedded Group audit trail

Agency admins can now view a Group's audit history directly from the Group page, making it easier to review changes without generating and waiting for a separate PDF or CSV report. Available to all customers when released.

[Embedded Audit Trail](#).

Availability: All regions

Improvement | UI/Accessibility

Parent file relationship in evidence audit trail

The Evidence Audit Trail header now displays the evidence checksum and parent checksum, making it easier to identify derived files and their parent files. Available in the Evidence Audit Trail header upon release.

Availability: All regions

Improvement | UI/Accessibility

Partner API updates

Changes to search API pagination limits

Starting in July 2026, Axon started a phased rollout enforcing a maximum offset of 10,000 pages for API clients using offset-based pagination. Requests that exceed this limit will receive an error response. To avoid disruption, migrate to cursor-based pagination before this limit takes effect in September — integrations using cursor-based pagination are not affected. For guidance on migrating, see the [Axon Partner API Guide](#).

Availability: All regions

Admin | Federal

Changes to search API rate limits

As previously announced, Axon finishes a phased rollout in September of per-agency rate limits on the Evidence Search API. Organizations that exceed the limit will receive an HTTP 429 Too Many Requests response with a Retry-After header indicating when to retry. If you have not already done so, update your integrations to handle 429 responses and implement retry logic with backoff - for more information, see the [developer documentation](#). Integrations that make high-volume or bulk search requests should use incremental, filtered queries instead of pulling large evidence collections in a single request. Contact Axon Support if you believe your workflows may be affected.

Availability: All regions

Admin | **Federal**

Axon Evidence

AI Generated Summaries of Images and Documents

You can now identify and review relevant information across more file types with Brief One AI summaries, available for documents and images in addition to video transcripts. When supported file types, like PDFs, Word documents, text files, and common image formats are uploaded to a case, the system generates a concise summary highlighting key facts and details.

Learn more about [Brief One for Axon Evidence](#).

Availability: CA1, US1

Improvement | **AI Era Plan**

Attribute Search

Attribute Search uses clothing and accessory descriptions to quickly locate human forms across evidence. It is now available for all AI Era Plan customers, or those who have purchased it as a standalone subscription. Attribute Search is included with Unlimited Smart Detection, and is on by default for users with the **Start and View Smart Detection** permission enabled.

Learn more about [Attribute Search](#).

Availability: US1, US3, US4, CA1, AU1, UK2

New | **AI Era Plan** | **Federal**

Bulk metadata actions support up to 5,000 items

Evidence ID (External ID), Category, Tags, and Custom Metadata bulk actions now support selections of up to 5,000 items.

With the increase in supported selections, bulk actions behaviors are changing to a Synchronous/Asynchronous process. Selections of 500 or fewer complete immediately. Selections for 500+ items will run asynchronously in the background, and you receive a notification when processing completes. As we work to increase our bulk action volumes, the asynchronous model will support future increases and stability.

Learn more about [Bulk actions](#).

Availability: All regions

Improvement

New Investigate Side Panel in Axon Evidence

Organizations with **Axon Investigate** and **Third-Party Video Support** now have a new **Investigate** side panel. Select evidence you want to play back, then select the Investigate tab to open the Clarifications space, and apply a filter without downloading the file or using a separate application. Stabilization is the first filter available. It smooths shaky video so you can follow the action, identify what's in frame, and present the footage clearly. Clarifications are off by default and require the Clarification permission under Admin > Roles & Permissions > Investigate Cloud.

Availability: All regions

New | Admin

Redesigned document viewer

The document viewer has been redesigned with a new thumbnails and table-of-contents side panel, continuous scrolling with support for mixed-orientation documents, and single/double-page facing layouts with cover pages. Expanded keyboard navigation makes it easier to move through longer documents without leaving the keyboard.

Learn more about [Viewing document evidence](#).

Availability: All regions

Improvement

Stabilization in Clarifications

Stabilization is the first filter in Clarifications, which requires Axon Investigate with Third-Party Video Support and the Clarification permission allowed. Body-worn camera footage recorded on the move, such as running down an alley, can bounce so much that it is hard to tell what is in front of the camera. Stabilize that video directly in Axon Evidence, without downloading the file or using separate software, so you can follow the action and present the footage clearly. Advanced settings control edge cropping and interpolation, and additional filters — brightness and contrast, crop, rotate, and lens distortion correction — arrive over the coming months.

Learn more about [Clarifications](#).

Availability: All regions

New | Admin

Video Stitching moves to a side panel

Build a stitch from a side panel instead of Review mode. Select the videos you want, order the clips, and submit. Stitching runs in the background and you receive an email when the new evidence is ready. Stitching requires Axon Investigate with Third-Party Video Support, and your administrator must allow the Stitching permission, which is not allowed by default.

Learn more about [Video Stitching](#).

Availability: All regions

Improvement | Admin

Axon Auto-Tagging

Voice tagging in AI Auto-Tagging (Alpha release)

Voice Tagging is now available as part of an Alpha release. Categorize body-worn camera evidence hands-free, immediately after a recording ends. When a recording stops, your camera prompts you to press and hold the double button to start voice tagging. Speak a category name, and AI Auto-Tagging transcribes it, matches it to your available categories, applies the category to the evidence metadata, and confirms by voice.

Learn more: [Voice Tagging](#).

Learn more about [Alpha and Beta features](#).

Availability: US1, AU1, CA1, UK2

New | Alpha | Admin | AI Era Plan

Axon Community Request

Configure custom metadata for requests

Administrators can now choose up to 10 custom metadata fields to appear on the create request page for users to populate during the creation process. This will only be for new requests following this release.

Learn more about [Community Request settings](#).

Availability: All regions

New | Admin | Federal

Expanded Victim and Community notification workflows

Improvements to Community Request now support broader Victim and Community notification workflows. Enable sharing of documents, victim resources, and other information. Community-facing portals receive a UI refresh and are secured with one-time passcode (OTP) authentication.

Availability: All regions

Improvement

Increased file upload limits for Community Request

The maximum number of files that can be submitted per request has increased from 25 to 100. Per-file (60 GB) and per-link (200 GB) size limits will remain unchanged. This change is for all request types except Public Portals.

Availability: All regions

Improvement | Federal

My90 is moving to Community Surveys

For organizations utilizing My90, we will begin the migration over to the new **Community Surveys** platform. Your existing surveys and data will move onto the Community Surveys platform so everything lives in one modern tool.

Why Community Surveys

Community Surveys is the next-generation replacement for My90. The new platform is built on Axon Community and is designed to help agencies manage community feedback with less manual effort and more actionable insight. Key capabilities include:

- **Self-service survey management and creation** — Create, edit, duplicate, and manage surveys without relying on My90 workflows or external tooling.
- **Automated reporting** — Configure scheduled reports so stakeholders receive updated survey results on a recurring basis.
- **Sentiment analysis** — Review response sentiment to quickly understand community perception and identify trends in feedback.
- **Modern analytics and dashboards** — Explore survey response data with interactive reporting designed for day-to-day agency use.
- **Integrated Community platform** — Built to support upcoming enhancements, planned AI capabilities, and deeper integration with other Community products, including Community Notifications and Community Request.

The Community Surveys experience is updated from My90. You may notice differences in layout, navigation, and how some workflows are organized.

What to expect during migration

- Your organization will be notified when migration starts and when it completes.
- You may experience brief, limited downtime while migration is in progress.
- After migration, sign in to **Community Surveys** to review your migrated surveys, responses, and settings.

Community Notifications integration

Organizations that purchased **My90** or the new **Community Link** tool also have access to **Community Notifications**, which supports self-service management of 911 / CAD updates to community members. This self-service management also lets your organization **select which calls receive a Community Survey**.

For more information, see [Community Notifications](#).

Admin actions after migration

Agency administrators should complete the following after migration:

1. **Automated reports:** Re-establish automated reports in Community Surveys, including how often you receive updated information.
2. **Interactive dashboards:** Interactive dashboards will be **automatically created** for your organization based on your migrated survey data. Review these dashboards and make adjustments as needed to select your preferred **graphics, summary**

statistics, and **other display options** to match your organization's preferences. We will continue to expand additional data visualization options in Community Surveys over upcoming releases.

3. **Public embedded forms:** If your agency uses publicly embedded forms, update the form in **Advanced settings** and copy the new iframe embed code for your website.

For help working with the new tool, see [Community Surveys overview](#).

If you have questions or need support during migration, contact support@axon.com.

Learn more about [Community Surveys](#).

[Community Notifications](#).

Availability: All regions

Admin

Case Management

Advanced Sharing is available for early access in the UK

Share cases with partner organizations through governed collaborations, so recipients work from current case information instead of one-time downloads or copied cases. Advanced Sharing requires the redesigned Axon Evidence, and an administrator must complete the Advanced Sharing setup and create a default sharing policy before users in your organization see sharing options. While you evaluate Advanced Sharing, Axon recommends enabling the redesigned Axon Evidence and Advanced Sharing in a test organization rather than in your live account.

Learn more about [Advanced sharing](#).

[Share a case with Advanced Sharing](#).

Availability: UK2

New | **Admin**

Case identifiers in download link emails and file names

Download link emails and downloaded file names now carry the case identifier, so you can tell which case a download belongs to from your inbox without opening the email, the link, or the package. This makes concurrent downloads easier to tell apart and easier to find again later.

Learn more about [Case sharing](#).

Availability: All regions

Improvement

Control automatic evidence sharing with partner organizations

Stop new evidence from being shared automatically with a partner organization after the initial share, and send updates manually instead. Your organization decides what reaches a partner and when, matching the manual sync already available in Axon Justice.

Learn more about [Advanced sharing](#).

Availability: US4, US1, US3, CA1

Federal | New | Admin

Evidence Certificates in Advanced Sharing policies

Evidence certificates are completed forms that certify the integrity or chain of custody of evidence. Administrators can now include or exclude certificates in a sharing policy, so certificates travel with the evidence to the receiving organization only when the policy allows it.

Learn more about [Advanced sharing](#).

Availability: US4, US3, US1, CA1

New | Admin | Federal

Evidence Share Log in Advanced Sharing policies

Administrators can now include the evidence share log in a sharing policy. When the log is included, the receiving organization can view it in both the reference case and their imported copy, so they have the record of who the evidence has already been shared with.

Learn more about [Advanced sharing](#).

Availability: US4, US3, US1, CA1

New | Admin | Federal

Include marker reports in download packages

Add marker reports to a case or evidence download package alongside audit trails, transcripts, and the table of contents. Recipients receive the report with the evidence, so disclosure packages that require a marker report for every video no longer need one downloaded and re-uploaded by hand.

Learn more about [Case sharing](#).

Availability: All regions

New

Evidence viewing and playback

Play up to 12 videos in Multicam Playback

Review a complex incident from more angles in a single session. The grid resizes automatically as you add and remove videos, so the tiles stay as large as the video count allows.

Learn more about [Multicam playback](#).

Availability: All regions

Improvement

Third-Party Video playback for records management uploads

CCTV and other third-party footage uploaded through Axon Records now plays in the media player.

Availability: All regions

Improvement

View and extract embedded subtitles

Video evidence with an embedded .ass subtitle track displays subtitles during playback, and you can switch between tracks when more than one exists. Extraction can also burn the subtitles into every frame, so the exported file carries them outside Axon Evidence.

Availability: All regions

Improvement

Zip Preview support for Deflate64

ZIP files compressed with Deflate64 previously failed validation and could not be opened. Some compression tools select Deflate64 automatically for archives larger than 2 GB, so the largest uploads were the most affected.

Availability: All regions

Improvement

Redaction

Redaction templates

Reapply a saved set of redactions to one video or a whole batch. Capture the masks, text annotations, and watermarks from a Redaction Studio session and save them as a named template. Templates are useful in cases where sensitive content sits in the same position on every recording, like a dashboard display, a badge number, or a fixed telemetry overlay. They can also stamp an official watermark across every frame. Saving a template requires the **Modify** permission. Redaction templates will be available at the end of September.

Learn more about [Redaction templates](#).

Availability: All regions

New | Admin

Refreshed Redaction Studio layout and navigation

Redaction Studio now shows the editor and the right panel as two separate panels on a darker background, making the editing workspace easier to distinguish from supporting tools. The right panel uses a vertical icon rail with tab navigation, a title dropdown, and a collapse control, matching the navigation pattern used elsewhere in Axon Evidence. The icon rail replaces the panel toggle that was previously in the utility bar.

Learn more about [Redaction Studio](#).

Availability: All regions

Improvement | UI/Accessibility

Third Party Video Support

Expanded format support and improvements

This release includes expanded format support and improved playback reliability across a wide range of video systems.

Expanded Format Support & Improvements

- Liberty Player (.dcr): Improved handling of multi-channel audio recordings. Files containing multiple audio streams (such as courtroom recordings with separate channels for judge, plaintiff, defendant, and other participants) are now parsed and displayed as individual streams for forensically sound review.
- Clip Player (.exe): Rebuilt with a new parser for improved codec support, audio handling, and playback reliability. Multiple manufacturers use the Clip Player format, and this update provides a more consistent foundation for supporting those files going forward.
- Samsung (.bu): Added new format support.
- Samsara (.swf): Added new format support.
- IDIS: Added new format support, including HEVC (H.265) recordings.
- Motorola Solutions Envysion: Added support for multi-file exports.
- Ocularis (OnSSI / Qognify): Added support for legacy Ocularis exports.
- EverFocus (.avr): Added audio support.
- Bosch (.dxa): Improved multi-stream handling and timestamp parsing.
- Milestone (.blk): Improved audio/video pairing and support for additional audio variants.
- Panasonic: Improved support for .mp4 + .xml package file sets, and added support for multi-file exports covering both .mp4 and .vtt sets.
- Genetec: Improved channel name parsing for more accurate stream identification.
- View Commander: Updated parser for improved compatibility.

Additional Format Support

- DVR interview room recordings (.dvr): Fixed audio playback for interview room video/audio files.

Playback Changes

- Infinity (IMM4 / IMM5): IMM4 and IMM5 recordings now show as unsupported in Axon Evidence, including in Zip Preview, rather than attempting playback. These formats require the manufacturer's codec installed on the local machine to display accurately. Without it, playback is a best-effort approximation and is not forensically sound, so we no longer attempt it. To review this footage, download and install the codec from the Axon Investigate software product page on axon.com, then use Axon Investigate to prepare the files for playback. Your IT department can assist with installation. If you encounter an AVI that does not play, it may use a codec that requires local installation.

If you encounter an unsupported video format, contact support@axon.com.

Learn more about [Third-Party Video Support](#).

Availability: All regions

Improvement | Federal

Axon Capture

Axon Capture is retiring

Axon Capture will no longer receive updates or support after April 30, 2026, and will be removed from the App Store and Google Play on September 30, 2026. The Axon App now provides full feature parity, including photo, video, and audio capture with metadata tagging and upload to Axon Evidence, and it keeps your existing sign-in credentials, audit trail, media tagging, workflow controls, and organization-level settings and policy enforcement. Migrate to the Axon App before September 30, 2026 to avoid disruption at the cutoff.

Learn more about [Axon App](#).

Availability: All regions

Deprecated

Axon View

Axon View is retiring

Axon View will be removed from the app stores at the end of September 2026, and sign-in access will end in November 2026. **My Devices** in the Axon App now provides Axon View's core functionality, so you can switch with no loss of workflow. Migrate to the Axon App now to avoid disruption at the cutoff.

Learn more about [Axon App](#).

Availability: All regions

Deprecated

Evidence Upload XT

Close exits Upload XT when no upload is running

Selecting **Close** now exits Upload XT if no upload is active. If an upload is in progress, Upload XT minimizes to the system tray and keeps uploading in the background, so you can close the window without interrupting your work.

Learn more about [Getting started with Upload XT](#).

Availability: All regions

Improvement

Faster case and tag loading

Case and tag lists load in pages, so results appear sooner when you select a case or tag. Larger organizations with extensive catalogs see the biggest improvement.

Availability: All regions

Improvement

TSV file import in the Migration tab

Run larger, better-controlled migrations from the Migration tab. Upload XT validates your organization's custom metadata during TSV file import, so you can find missing required values before the migration starts. A single TSV file can now include both individual files and complete folders, with folder rows scanned recursively, and you can pause, resume, or cancel a running TSV migration. Specify a case folder directly in the TSV file to place evidence in the intended case folder during migration.

Learn more about [migration setup](#).

[Get started with Upload XT](#).

Availability: All regions

Improvement

Resolved issues

Axon Evidence

- We fixed a bug where the **Download** and **More actions** menu did not appear, and the evidence page navigation bar flickered, when opening evidence shared to an agency using a secure share link. Users can now access **Download** and **More actions** normally when viewing shared evidence.
- We fixed a bug on the evidence details page where saving External ID, title, category, or tag changes could close edit mode before the save completed, or even when a save failed. This caused users to lose unsaved changes or think their edits were saved when they were not. Edit mode now stays open until all saves succeed, the **Save** button shows a loading indicator while saving, and failed saves are surfaced so users can retry.

Coming soon

This section provides advanced notice about upcoming features.

Axon Evidence

Bulk actions for Title, Content Warning, and Evidence Groups

Bulk actions in Axon Evidence will soon expand to cover **Title**, **Content Warning**, and **Evidence Groups**, so more metadata can be updated across a larger selection of evidence from the evidence search page.

New

Vehicle name column

Identify the vehicle a recording came from by its assigned name, using the same vehicle names your organization already uses. The Vehicle name column is hidden by default — turn it on from table settings (gear button) on the evidence search page. Once enabled, Vehicle name is also included in search result exports.

Learn more about [Filter and table settings](#).

Availability: All regions

New | Federal

Cameras and sensors

Axon Body 4

Firmware Update Process Improvement for Axon Body Cameras

Axon Body 3, Axon Body Workforce, **Axon Body 4**, and Axon Body Mini cameras will receive an improvement to the firmware update process. No workflows will change for users or administrators. Devices that have been offline and missed recent updates may require two update cycles to become current. Available in all regions beginning September 2026.

Availability: All regions

Improvement

Firmware v1.2631 Releasing September 22nd

Firmware 1.2631 improves connectivity and camera reliability, including fixes for small recording, display, haptic feedback, and video mask behaviors.

The phased rollout began with early access devices on August 25, 2026, with general availability targeted for September 22, 2026 in all regions.

Availability: All regions

Improvement | Federal

Axon Body 3

Firmware Update Process Improvement for Axon Body Cameras

Axon Body 3, Axon Body Workforce, Axon Body 4, and Axon Body Mini cameras will receive an improvement to the firmware update process. No workflows will change for users or administrators. Devices that have been offline and missed recent updates may require two update cycles to become current. Available in all regions beginning September 2026.

Availability: All regions

Improvement

Firmware v1.2631 Releasing September 22nd

Firmware 1.2631 improves general connectivity, restores the LCD “Lights Off” icon after a power cycle, and improves haptic feedback consistency during recording. The phased rollout began with early access devices on September 9, 2026, with general availability targeted for September 22, 2026.

Availability: All regions

Improvement | Federal

Axon Body Workforce

Firmware Update Process Improvement for Axon Body Cameras

Axon Body 3, **Axon Body Workforce**, Axon Body 4, and Axon Body Mini cameras will receive an improvement to the firmware update process. No workflows will change for users or administrators. Devices that have been offline and missed recent updates may require two update cycles to become current. Available in all regions beginning September 2026.

Availability: All regions

Improvement

Axon Body Mini

Firmware Update Process Improvement for Axon Body Cameras

Axon Body 3, Axon Body Workforce, Axon Body 4, and **Axon Body Mini** cameras will receive an improvement to the firmware update process. No workflows will change for users or administrators. Devices that have been offline and missed recent updates may require two update cycles to become current. Available in all regions beginning September 2026.

Availability: All regions

Improvement

Axon Fleet

Disable ALPR Fleet Search in Axon Evidence (US1)

As of August 27 in US1, Agencies can now opt in to hide the ALPR Fleet Search tab in Axon Evidence, making Fusus the single place for ALPR searches and helping ensure required search-purpose information is captured consistently. CSMs can enable this setting for individual agencies; when enabled, users who access Fleet Search in Axon Evidence are redirected to Fusus ALPR Search.

[Learn more about Fusus ALPR Search.](#)

Availability: US1

New | **Improvement** | **Admin**

Fleet 2026 Q4 Interim Release v2.2634.4950

Smart Capture (General Availability) — Smart Capture is now generally available in Fleet Dashboard for agencies on eligible plans. The Smart Tray lets users quickly access recent Smart Captures and copy extracted data into third-party systems, such as RMS applications and NCIC lookups.

- The Fleet integration is disabled by default; contact your Axon representative to enable it. Users must also upgrade their Fleet firmware and Dashboard versions and restart the system for Smart Capture data and the Smart Capture evidence tab to appear in Fleet 3 Dashboard.

Performance and reliability — This release also improves ALPR record handling, evidence uploads, system stability, and security. No action is required.

See [Smart Capture Fleet reference \(end of the article\)](#).

Availability: CA1, US1

New | **Improvement**

Axon ALPR

Disable ALPR Fleet Search in Axon Evidence (US1)

As of August 27 in US1, Agencies can now opt in to hide the ALPR Fleet Search tab in Axon Evidence, making Fusus the single place for ALPR searches and helping ensure required search-purpose information is captured consistently. CSMs can enable this

setting for individual agencies; when enabled, users who access Fleet Search in Axon Evidence are redirected to Fusus LPR Search.

[Learn more about Fusus ALPR Search..](#)

Availability: US1

Improvement | New | Admin

Axon Device Manager

Axon Device Manager (ADM) v3.2631 Quality Improvements

ADM v3.2631 for Android and iOS, releasing September 15, 2026 includes behind-the-scenes improvements that increase reliability, reduce errors, and provide a smoother user experience.

Availability: All regions

Improvement | Federal

Resolved issues

Axon Body 4

Firmware v1.2631 Releasing September 22nd

- Addresses issue where devices would overheat and fail to boot
- Adds support for Pairing Icon when camera is connected to Axon App
- Fixes issue where some livestreams would display a momentary glitch

Axon Body 3

Firmware v.1.2631 Releasing September 22nd

- Adds support for Pairing Icon when camera is connected to Axon App

Coming soon

This section provides advanced notice about upcoming features.

Firmware v1.2637 Releasing October 27th

Axon Body 4 firmware 1.2637 is scheduled to release to Early Access customers starting October 6th, deploying in waves over three weeks, with general availability scheduled for October 27th. This release includes performance improvements.

Availability: All regions

Improvement | Federal

Axon Body 3

Firmware v1.2637 Releasing October 28th

Axon Body 3 firmware 1.2637 is scheduled to release to Early Access customers starting October 6th, deploying in waves over three weeks, with general availability scheduled for October 28th. This release includes performance improvements.

Availability: All regions

Improvement | Federal

Axon ALPR

Convert ALPR records to evidence from Fleet 3 Dashboard - Release Date Change

Previously announced as available August 21, 2026, this feature has been rescheduled, with a new release date to be determined. Once available, officers can convert ALPR reads or hits to evidence directly from the Fleet 3 Dashboard, add or edit evidence details before upload, and prioritize the converted record over video evidence uploads. Contact your Axon representative to enable access.

Availability: All regions

New

Outpost GA8 Release - October 2026

When released, Outpost will detect and record vehicles when a license plate is missing, blocked, or unreadable, with vehicle and context images that provide more information about the surrounding scene. This release also improves fixed-camera location accuracy and image quality in changing light conditions and resolves a rare issue that could interrupt plate processing during device updates or reboots. Available October 8, 2026.

Availability: All regions

New | Improvement | Federal

Axon View XL

View XL v1.36 Releasing in October

View XL 1.36 will no longer support Windows 8 or Windows 8.1 due to a required Electron framework security update. Devices running these operating systems cannot install View XL 1.36 or future releases and should be upgraded to Windows 10 or later to continue receiving security updates, improvements, and new features. The Windows installer size will also increase to up to 195 MB with this release. Release is scheduled in early October.

This release also includes reliability improvements that reduce errors and support a smoother experience.

Availability: All regions

Improvement | Federal | Admin

TASER Energy Weapons

Axon Dock firmware 3.25

Firmware version 3.25 for TASER weapons and Axon Body 2 docks includes security and encryption updates. The release also includes updates that address third-party software and operating system security issues. The update applies automatically and does not require any setup or workflow changes. This will be available for Early Access devices September 16 with general availability October 14.

Availability: All regions

Improvement

TASER 10 Probe Connection Summary

TASER 10 deployment log PDFs will include a Probe Connection Summary that shows each deployed cartridge's connection status (Connected or Not Connected), and its connected duration. This gives officers and supervisors a clearer view of probe connection outcomes without requiring them to interpret the detailed Energize Timeline.

Learn more about [device logs](#).

Availability: All regions

Improvement

TASER Weapons Health Digest

Administrators and armorers will be able to receive periodic email summaries identifying TASER weapons that may require attention, including overdue docking, firmware updates, or function tests. The email links to the TASER Program Dashboard, where they can review the relevant device and officer information. Administrators turn this feature on or off for the agency from the TASER Program Dashboard, and individual recipients can opt out of the emails under My Notifications in their profile settings.

Learn more about [TASER Program Dashboard](#).

Availability: All regions

New | Admin

TREND TASER 10 Quarterly Report

TREND-entitled agencies with TASER 10 using TREND in Axon Evidence can download a quarterly PDF report generated from TASER 10 device logs, providing agency-specific insights into TASER energy weapon usage, inventory readiness, and program health.

The report summarizes the previous quarter, includes quarter-over-quarter comparisons for applicable metrics, and shows up to five quarters of historical data. Regularly docking TASER 10 energy weapons helps ensure the report contains the most complete data for TASER program management.

Learn more about [TREND](#).

Availability: US1

New | Improvement

TREND in Axon Evidence

TREND dashboards are moving from Axon Standards into the TASER energy weapons page in Axon Evidence, giving TASER program managers, administrators, and trainers one place to manage their TASER program. The Axon Evidence experience includes updated visuals, interactive graphs, and new capabilities such as the TREND TASER 10 Quarterly Report. Several reports are available now, with the remaining reports migrating by the end of 2026, while the existing Axon Standards experience remains available until then.

Learn more about [TREND](#).

Availability: US1

Improvement | Admin

Resolved issues

- Fixed an issue where the Alert panel count could be out of sync with the TASER Program Dashboard metrics count for interposer bucket replacements.
- Fixed an issue where some TASER energy weapon batteries caused repeated TASER Dock restarts and interrupted communication with other docked batteries.
- Fixed an issue where Evidence Sync incorrectly required users to have both the "TASER Weapon Logs Administration (manage TASER Weapon logs)" and "Device

Administration (register, reassign, and manage non-TASER Weapon devices)" permissions to download TASER X2 logs. Users now only need the "TASER Weapon Logs Administration" permission to view and download X2 logs.

Justice

AI Generated Summaries of Images and Documents

You can now identify and review relevant information across more file types with Brief One AI summaries, available for documents and images in addition to video transcripts. When supported file types, like PDFs, Word documents, text files, and common image formats are uploaded to a case, the system generates a concise summary highlighting key facts and details.

Learn more about [Brief One for Axon Justice](#).

Availability: US1, CA1

Improvement | AI Era Plan

Bulk actions on evidence

Make the same change across multiple files in one pass. Bulk actions now cover making edits to selected evidence for ID and Category so routine work on a large case no longer means opening files one at a time. Select what you want to work with, and an action bar appears at the bottom of the page. The action bar shows how many items you have selected, and the actions available depend on where you are working.

Learn more about [Bulk actions](#).

Availability: US1, US3, US4, AU1, CA1, EU1, NL1, LA1

Improvement

Redesigned document viewer

The document viewer has been redesigned with a new thumbnails and table-of-contents side panel, continuous scrolling with support for mixed-orientation documents, and single/double-page facing layouts with cover pages. Expanded keyboard navigation makes it easier to move through longer documents without leaving the keyboard.

Learn more about [Viewing document evidence](#).

Availability: All regions

Improvement

Stabilization in Clarifications

Body-worn camera footage recorded on the move, such as running down an alley, can bounce so much that it is hard to tell what is in front of the camera. Stabilize that video directly in Axon Justice, without downloading the file or using separate software, so you can follow the action and present the footage clearly. Stabilization is the first filter in Clarifications, which requires Axon Investigate with Third-Party Video Support and the Clarification permission allowed. Advanced settings control edge cropping and interpolation, and additional filters — brightness and contrast, crop, rotate, and lens distortion correction — arrive over the coming months.

Learn more about [Clarifications](#).

Availability: All regions

New | Admin

Video Stitching moves to a side panel

Build a stitch from a side panel instead of Review mode. Select the videos you want, order the clips, and submit. Stitching runs in the background and you receive an email when the new evidence is ready. Stitching requires Axon Investigate with Third-Party Video Support, and your administrator must allow the Stitching permission, which is not allowed by default.

Learn more about [Video Stitching](#).

Availability: All regions

Improvement | Admin

Coming soon

This section provides advanced notice about upcoming features.

A Stitch control on the evidence toolbar

Start a stitch without going through Review; title screens with duration, disclaimer screens, and transition frames between clips in grey, black, or white; organization defaults for those screens in the Admin Console; and stitched output listed in the Related tab.

Learn more about [Video Stitching](#).

Availability: All regions

Improvement | Admin

Change log

The table below contains a log of all changes made to these release notes.

Date	Product	Description of change
September 29, 2026		Initial notes created

If you have any questions about the information in this release, contact your Axon representative or Technical Support.

1-800-978-2737 ext. 4

support@axon.com

Do you have feedback about Axon's release notes? Submit it [here](#).

Sincerely,

The Axon Team

Axon Enterprise, Inc.